

Dataset Introduction-MPIIGaze

File Structure

```
MPIIGaze
|
|-Label
|   |
|   |-{subject}.label
|
|-Image
|   |-{subject}
|       |-face
|       |-left
|       |-right
|           |-1.jpg
|           |-2.jpg
|           |
|           |
|           |
|           |
```

.label File Format

Each `.label` file contains the data of one subject. Each line contains the data of one image. The first line in `.label` file is the name of contained variables. Variables are separated by space. As for variables contain more than one value. values are separated by `,`.

- **Image** - *string* - Path of normalized eye image relative to `../Image/`.
- **Origin** - *string* - Denotes the origin image.
- **WhichEye** - *string* - Denote which eye the frame is.
- **3DGaze** - *(3,)* - Ground truth of normalized 3D gaze direction vector.
- **3DHead** - *(3,)* - Ground truth of normalized 3D head orientation vector.
- **2DGaze** - *(2,)* - Ground truth of normalized 2D gaze direction vector *i.e.* yaw and pitch.
- **2DHead** - *(2,)* - Ground truth of normalized 2D head orientation vector *i.e.* yaw and pitch.
- **Rmat** - *(3,)* - Rotation vector from original Camera Coordinate System (CCS) to the normalized CCS.
- **Smat** - *(3,)* - The diagonal elements of the scale matrix used in the normalization procedure.
- **GazeOrigin** - *(3,)* - Origin of 3D gaze vector in the normalized CCS.

Getting Start.

You could read the line in `.label` file for reading image data.

Assuming the root path is `/home/MPIIGaze`. You could:

```
import os
import cv2

# line; One line in `.label` file.
imroot = '/home/MPIIGaze'

image_path = os.path.join(imroot, 'Image', line.split(' ')[0])

image = cv2.imread(image_path)
label = line.strip().split(' ')[3].split(",")
label = np.array(label).astype('float')
```